

**Chapter 4 Documents**

TEXT      Text Header Table .....2

TLRD      Text By Date Last Reviewed .....5

TTCD      Text By Text Type Code Table .....7

TXLN      Text Line Table .....9

TXL2      THIS SCREEN NO LONGER AVAILABLE.....11

TXMA      Text By Maintaining Agency Number .....13

TXST      Text By Status Code .....15

TXTL      Text By Title.....17

**TEXT**

**Text Header Table**

```
ENTER FUNCTION: ..... TRANS: TEXT
TEXT HEADER TABLE
KEY IS TEXT REFERENCE NUMBER
TEXT REF NUMBER.....: .....
TEXT TYPE CODE.....: ... :
TITLE..:.....:.....
STATUS CODE.....: . :
STATUS CHANGE DATE.:
MAINTAINING AGENCY.: ..... :
LAST REVIEW DATE...: .....
BUYER LAST REVIEWED: ... :
USER ID LAST CHANGE:
DATE LAST CHANGED..:
```

**Purpose**

The purpose of the Text Header Table is to provide the user with the capability of adding, changing, deleting and inquiring Text Header Records. The Text Header Records can be called into the program in the Solicitation process. Security for these records is based on the user and the Maintaining Agency of the Text.

**Screen**

**Characteristics**

Add, Change, Delete and Inquire Text Header Table.

**Procedure**

**Cross-Reference**

Chapter 2 Text Database Maintenance;

- 1.1 Add Text Header Table
- 1.2 Change Text Header Table
- 1.3 Delete Text Header Table
- 1.4 Inquire Text Header Table

**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Date	8	Protected. Maintained by system. Current date.
Time	8	Protected. Maintained by system. Current time.
Term	8	Protected. Maintained by system. Terminal ID logged on to transaction.
Text Ref Number	6	Unprotected. Key. Required on adds. This is a user assigned number that is unique in the text header record table. If left blank the program will return with the first record in the database.
Text Type Code	3	Unprotected. Required on adds. Must be a valid entry in BTAB Table TP (Text Type Code).
Text Type Title	30	Protected. The interpretation of the text type code from BTAB Table TP (Text Type Code).
Title	70	Unprotected. Required. User assigned title which can be used in locating the text at a later date.
Status Code	1	Unprotected. Reflects the status of the text. Must be a valid entry in the BTAB Type Table TS (Text Status Code).
Status Code Title	30	Protected. The interpretation of the status code from BTAB Table TS (Text Status Code).
Status Change Date	8	Protected. The date of the last change to the status code. Maintained by the system.
Maintaining Agency	6	Unprotected. Required on add. The agency number of the responsible (maintaining) agency.
Maintaining Agency Title	35	Protected. The title of the agency as provided from the Agency database.
Last Review Date	8	Unprotected. This date must be valid and can not exceed the input date.
Buyer Last Reviewed	3	Unprotected. The code identifying the buyer making the last review. This code must be valid in the ABUY Table.
Buyer Name	35	Protected. The name of the buyer from the ABUY Table.

**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
USERID Last Change	4	Protected. The user ID of the person making the last change to this record.
Date Last Changed	8	Protected. The date of the last change to this record.



**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Date Last Reviewed	10	Unprotected. Key. Required. If left blank the system will return with the earliest date in the database. If date is input the screen will return with that date and the first text reference number for that date. Format is CCYY MM DD.
Text Reference	6	Unprotected. Key. If left blank the system will return with the first text reference number for that date in the database. If input with the desired date the system will return with the desired combination.



**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Date	8	Protected. Maintained by system. Current date.
Time	8	Protected. Maintained by system. Current time.
Term	8	Protected. Maintained by system. Terminal ID logged on to transaction.
Text Type	3	Unprotected. Key. Required. Must be valid entry in BTAB Table TP (Text Type Code).
Text Type Title	30	Protected. The interpretation of the text type code from BTAB Table TP (Text Type Code).
Text Ref	6	Unprotected. Key. If left blank the system will return with the first text reference number in the database.
Text Title	70	Protected. The title of the text reference number from the TEXT database.



**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Date	8	Protected. Maintained by system. Current date.
Time	8	Protected. Maintained by system. Current time.
Term	8	Protected. Maintained by system. Terminal ID logged on to transaction.
Text Ref Number	6	Unprotected. Key. Specifies the Text Reference number that will be added or viewed.
Title	70	Protected. The title of the text reference number from the Text database.
Maintaining Agency	6	Protected. The agency responsible for the maintaining the text as provided from the Text database.
Agency Title	30	Protected. The title of the agency from the Agency database.
Status Code	1	Protected. The status code from the Text database.
Status Title	30	Protected. The interpretation of the status code from BTAB Table TS (Text Status Code).
Text Action	1	Unprotected. Must be a valid text action code. Valid codes are:  T - Top B - Bottom U - Page up D - Page down R - Relative I - Insert X - Delete
Line Number	4	Unprotected. Used with text action 'R' to indicate the relative number of lines to scroll.
Line Total	4	Protected. Indicates the total number of lines associated with this text file.
Text Line	70	Unprotected. Free form text line at the users discretion. A (.) in the first position indicates a null line. Null lines are not allowed at the beginning of text lines or between text lines. Blank lines are created by changing the (.) to a space.

**TXL2 THIS SCREEN NO LONGER AVAILABLE**

```
ENTER FUNCTION: ..... TRANS: TXL2
TEXT LINE TABLE #2
KEY IS TEXT REFERENCE NUMBER
TEXT REF NUMBER.....: .....
TITLE...:
MAINTAINING AGENCY.: :
STATUS CODE.....: :
SCROLL ACTION.....: LINE NUMBER: LINE TOTAL:
ACT -----1-----2-----3-----4-----5-----6-----7
..
..
..
..
..
..
..
..
..
..
```

**Purpose** The purpose of the Text Line Table #2 is to provide the user with the ability to insert or delete lines of text from the Text Line Table #1 (TXLN). Access to this table can only be achieved by leafing from TXLN. When appropriate action has been indicated, the system will automatically return to TXLN upon depressing enter key to process the indicated action.

**Screen Characteristics** Delete/Insert Text Line Table.

**Procedure Cross-Reference** Chapter 2 Text Database Maintenance;

2.3 Delete/Insert Text Line Table.

**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Date	8	Protected. Maintained by system. Current date.
Time	8	Protected. Maintained by system. Current time.
Term	8	Protected. Maintained by system. Terminal ID logged on to transaction.
Text Ref Number	6	Protected. Key. Specifies the text reference number that will be added or viewed.
Title	70	Protected. The title of the text reference number from the Text database.
Maintaining Agency	6	Protected. The agency responsible for the text.
Agency Title	30	Protected. The title of the agency as provided from the Agency database.
Status Code	1	Protected. The status code from the Text database.
Status Title	30	Protected. The interpretation of the status code from BTAB Table TS (Text Status Code).
Scroll Action	1	Protected. The scroll action code carried forward from the TXLN screen.
Line Number	4	Protected. The line number field carried forward from the TXLN screen.
Line Total	4	Protected. Indicates the total number of lines associated with this text file.
Act(ion Code)	2	Unprotected. 'I' indicates insertion which will occur after the line. 'D' is used to indicate delete. 'D' followed by a number will cause a delete of that many lines. The number of delete lines cannot be greater than the number of lines displayed on the screen from the point of delete.
Text	70	Protected. A display of text carried forward from the TXLN screen. Any change action will cause the screen to return to TXLN with the appropriate action taken.



**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Date	8	Protected. Maintained by system. Current date.
Time	8	Protected. Maintained by system. Current time.
Term	8	Protected. Maintained by system. Terminal ID logged on to transaction.
Maintaining Agency	6	Unprotected. Key. If left blank and the user has the security for that agency the screen will return with the first agency in the database.
Agency Title	30	Protected. The title of the agency as provided from the Agency database.
Text Ref	6	Unprotected. Key. If left blank the system will start the list with the first text reference number in the database.
Title	70	Protected. The title of the text reference number from the Text database.



**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Date	8	Protected. Maintained by system. Current date.
Time	8	Protected. Maintained by system. Current time.
Term	8	Protected. Maintained by system. Terminal ID logged on to transaction.
Status Code	1	Unprotected. Key. If left blank the system will return with the first status code in the database.
Status Code Title	30	Protected. The interpretation of the status code from BTAB Table TS (Text Status Code).
Text Ref	6	Unprotected. Key. If left blank the system will return with the first text reference number for the status code specified.
Title	70	Protected. The title of the text reference number from the Text database.



**Field Completion**

<u>Field</u>	<u>Size</u>	<u>Description</u>
Title	70	Unprotected. Key. Required. The title or part of the title from the Text database. If left blank the system will return with the first title in the database.
Text Ref	6	Protected. The text reference that corresponds to the title specified.